

# AUTOCOUNT ACCOUNTING 2.0 BASIC TRAINING 8 NOV 2022

#### Installation


- SERVER/STANDALONE
  - Install Microsoft SQL Server
    - sa
    - oCt2005-ShenZhou6\_A2006
  - AutoCount
  - AutoCount Server Setup

https://wiki.autocountsoft.com/wiki/Category:AutoCount\_Accounting\_2.0:Release\_Note

- Client PC
  - AutoCount

# What happen if AutoCount Server 141 or 142, AutoCount rev is lower than rev 203?





```
System.TypeInitializationException: The type initializer for 'AutoCount.Data.ScheduledBackup.LicenseProfile' threw an exception. --->
System.TypeInitializationException: The type initializer for "AutoCount.Data.ScheduledBackup.SecurityUtils" threw an exception, ---> System.Exception: Get
Unique Hardware ID error
 at AutoCount.Data.ScheduledBackup.LicenseDeviceServiceHelper.GetUniqueDeviceiDft
 at AutoCount.Data.ScheduledBackup.SecurityUtils.GetUniqueDeviceID()
 at AutoCount.Data.ScheduledBackup.SecurityUtils...cctor()
 --- End of inner exception stack trace ---
 at AutoCount.Data.ScheduledBackup.LicenseProfile..cctor()
 --- End of inner exception stack trace ---
 at AutoCount.Data.ScheduledBackup.LicenseProfile.LoadDataSet()
 at AutoCount.Data.ScheduledBackup.FormLicenseControlPanel..ctor(String[] args)
 at AutoCount.Data.ScheduledBackup.App.OnStartup(StartupEventArgs e)
 at System.Windows.Application.<.ctor>b_1_0(Object unused)
 at System.Windows.Threading.ExceptionWrapper.InternalRealCall(Delegate callback, Object args, Int32 numArgs)
 at System.Windows.Threading.ExceptionWrapper.TryCatchWhen(Object source, Delegate callback, Object args, Int32 numArgs, Delegate catchHandler)
 at System.Windows.Threading.DispatcherOperation.InvokeImpl()
 at System.Windows.Threading.DispatcherOperation.InvokeInSecurityContext(Object state)
 at MS.Internal.CulturePreservingExecutionContext.CallbackWrapper(Object obj)
 at System.Threading.ExecutionContext.RunInternal(ExecutionContext executionContext, ContextCallback, Object state, Boolean preserveSyncCtx)
 at System.Threading.ExecutionContext.Run(ExecutionContext executionContext, ContextCallback, Object state, Boolean preserveSyncCtx)
 at System.Threading.ExecutionContext.Run(ExecutionContext executionContext, ContextCallback, Object state)
 at MS.Internal.CulturePreservingExecutionContext.Run(CulturePreservingExecutionContext executionContext, ContextCallback, Object state)
 at System.Windows.Threading.DispatcherOperation.Invoke0
 at System.Windows.Threading.Dispatcher.ProcessQueue()
 at System.Windows.Threading.Dispatcher.WndProcHook(IntPtr hwnd, Int32 msg, IntPtr wParam, IntPtr IParam, Boolean& handled)
 at MS.Win32.HwndWrapper.WndProc(IntPtr hwnd, Int32 msg, IntPtr wParam, IntPtr IParam, Boolean& handled)
 at MS.Win32.HwndSubclass.DispatcherCallbackOperation(Object o)
 at System.Windows.Threading.ExceptionWrapper.InternalRealCall(Delegate callback, Object args, Int32 numArgs)
 at System.Windows.Threading.ExceptionWrapper.TryCatchWhen(Object source, Delegate callback, Object args, Int32 numArgs, Delegate catchHandler)
 at System.Windows.Threading.Dispatcher.LegacyInvokeImpl(DispatcherPriority, Priority, TimeSpan timeout, Delegate method, Object args, Int32 numArgs)
 at MS.Win32.HwndSubclass.SubclassWndProc(IntPtr hwnd, Int32 msg, IntPtr wParam, IntPtr IParam)
 at MS.Win32.UnsafeNativeMethods.DispatchMessage(MSG& msg)
 at System.Windows.Threading.Dispatcher.PushFrameImpl(DispatcherFrame frame)
 at System.Windows.Threading.Dispatcher.PushFrame(DispatcherFrame frame)
 at System.Windows.Application.RunDispatcher(Object ignore)
 at System.Windows.Application.RunInternal(Window window)
 at System.Windows.Application.Run(Window window)
 at AutoCount.Data.ScheduledBackup.App.Main()
```

#### Maintenance:

- 1. Account Maintenance
- 2. General Maintenance
  - User Maintenance
  - Access Rights
  - Multi Currency
  - Document Numbering Format
  - Project Maintenance
  - Posting Account Group
- 3. Debtor Maintenance
- 4. Creditor Maintenance
- 5. Stock Maintenance
  - Costing Method
  - Basic UOM

- 6. Tax
  - Sales Tax
  - Service Tax
- 7. Purchase
- 8. Sales
  - View Flow
  - Save as template
  - Save as draft
- 9. Stock Document
  - Recalculate
  - Stock Card
  - Stock Balance
- 10. GL/AR/AP
  - Ledger
  - Trial Balance
  - Profit and Loss
  - Advance Financial Report
  - Balance Sheet

## Opening Balance Maintenance

- Start Date = Actual Data Start Date
  - Start Date = 1/1/2022
  - Actual Data Start Date = 1/1/2022
  - Closing as at 31/12/2021.
  - ONLY Debtor/Creditor must maintain as PAST INVOICE (AR/AP INV)
  - Other account direct key in inside opening.

#### Year-to-Date Maintenance

- Start Date != Actual Data Start Date
   Start Date = 1/1/2022
   Actual Data Start Date = 1/5/2022
  - TICK checkbox of Balance B/F in the last month of Year-To-Date Balance.
  - DO NOT input Opening Balance
  - For **Debtor/Creditor** balances, must maintain the **Past/YTD document** from **AR/AP Invoice/CN/Payment**.
  - Other account direct key in at YTD Maintenance.
    - (refer Profit & Loss as at 30/04/2022 and Balance Sheet as at 30/04/2022 from existing software)

# Cash Book vs AR/AP Payment

Cash Book	AR/AP Payment
One time payment	
No debtor/creditor.	Debtor/ Creditor is COMPULSORY
Cannot Knock Off Invoice	Can Knock Off Invoice

# AR/AP VS SALES PURCHASE INVOICE

AR/AP INV	DELIVERY ORDER/SALES INVOICE	PURCHASE INVOICE
Cannot Print	Can Print	Can Print
NO Stock	Involve Stock OUT STOCK	Involve Stock IN STOCK
Posting G/L Account	Posting G/L Account	Posting G/L Account
CANNOT post to Sales/Purchase Invoice.	Post to AR INV	Post to AP INV

#### SALES DOCUMENT VS PURCHASE DOCUMENT

SALES DOCUMENT	PURCHASE DOCUMENT
Delivery Oder = OUT STOCK	Goods Receive Note: IN STOCK
Invoice = OUT STOCK + POSTING GL ACCOUNT	Purchase Invoice : IN STOCK + POSTING GL ACCOUNT
Cash Sales	Cash Purchase

## **GL** Posting Account

- Posting Account Group
  - Priority 1 = Posting Account Group
    - General Maintenance Posting Account Group Maintenance
    - Debtor Maintenance Others tab Posting Account.
  - Priority 2 = Stock Group
    - Stock Stock Group Maintenance
  - Priority 3 = Default Setting.
    - Tools Option GL Default Account.